



<http://www.kiwi-little-things.com> Vintage Pattern

Downing No. 906 20 cents

KAIAPOI

Cable Panelled Pullover with Saddle
Shoulders and Crew Neck using
Kaiapoi Triple Crepe Wool.

4 Sizes 28-34 Chest or Bust



Cabled Panelled Pullover with Saddle Shoulders and Crew Neck. 4 sizes: 28-34 Chest or Bust.

13 1/2 grams
more wool

MATERIALS

✓ Kaiapoi Triple Knitting Qualities: 16 (18: 21: 23) ozs. One pair each Nos. 6 and 8 knitting pins. Cable needle.

MEASUREMENTS

To fit sizes 28 (30: 32: 34) inch chest or bust loosely. Length of centre back from below neckband: 17 1/2 (19 1/2: 21: 22 1/2) ins. Sleeve seam: 13 (14 1/2: 16: 16 1/2) ins.

TENSION

4 1/2 sts and 5 1/2 rows to one square inch over stst on No. 6 pins or any size pins which will give tension stated.

IMPORTANT: Please check your tension before starting this garment by knitting a sample at least 2 inches square. If you obtain more stitches per inch than specified, change to larger pins. If less, use smaller pins.

ABBREVIATIONS

K, knit; p, purl; sts, stitches; tog, together; rep, repeat; inc, increase; dec, decrease; beg, begins(ing); cont, continue (s)(ing); rem, remains(ing); ins, inches; alt, alternate; ptn, pattern; fin, finish (es)(ing); fol, follows(ing); meas, measures(ed); wl, wool; stst, stocking stitch (right side k, wrong side p); Tw 2 F, twist 2 front thus:—K into the front of the 2nd on left hand pin, then k into the front of the first st and let both loops fall off left hand pin together; Tw 2 B, twist 2 back thus:—Take right hand pin to back of work and k into the back of the 2nd st on left hand pin, then k into the front of

the first st and let both loops fall off left hand pin together; C 6 F, cable 6 front thus:—Place next 3 sts on to cable needle and leave at front of work, k 3, then k the 3 sts from cable needle; C 6 B, cable 6 back thus:—Place next 3 sts on to cable needle and leave at back of work, k 3, then k 3 sts from cable needle; R.S., right side, W.S., wrong side.

BACK: With No. 8 pins cast on 65 (71: 75: 81) sts and work in rib as fol:

1st row: K 1, * p 1, k 1, rep from * to end.

2nd row: P 1, * k 1, p 1, rep from * to end.

Rep these 2 rows until 11 rows in all have been worked, thus fin with a first row.

Next row: Inc into the first st, rib 20 (23: 25: 28) sts, inc 11 sts evenly across next 23 sts, rib to last st, inc into last st. 78 (84: 88: 94) sts.

Change to No. 6 pins and work in ptn as fol:

1st row: K 22 (25: 27: 30) sts, p 2, Tw 2 F, Tw 2 B, p 2, k 18, p 2, Tw 2 F, Tw 2 B, p 2, k to end.

2nd and all alt rows: P 22 (25: 27: 30) sts, k 2, p 4, k 2, p 18, k 2, p 4, k 2, p to end.

3rd row: K 22 (25: 27: 30) sts, p 2, Tw 2 F, Tw 2 B, p 2, C 6 F, k 6, C 6 B, p 2, Tw 2 F, Tw 2 B, p 2, k to end.

5th row: As first row.

7th row: K 22 (25: 27: 30) sts, p 2, Tw 2 F, Tw 2 B, p 2, k 3, C 6 B, C 6 F, k 3, p 2, Tw 2 F, Tw 2 B, p 2, k to end.

8th row: As 2nd row.

Rep these 8 rows until work meas 10 1/2 (12: 13: 14) ins or desired length, fin with a W.S. row.

Shape Armholes: Cast off 3 (4: 4: 5) sts at beg next 2 rows. Dec one st at each end of the next and every fol alt row until 62 (66: 70: 74) sts rem. Cont straight until armhole meas 6 (6½: 7: 7½) ins (meas in a straight line parallel with beg armhole shaping), fin with a W.S. row.

Shape Shoulders: Cast off 6 (6: 7: 7) sts at beg next 2 (6: 2: 6) rows, then cast off 5 (0: 6: 0) sts at beg next 4 (0: 4: 0) rows. Cont straight in ptn on rem 30 (30: 32: 32) sts for 4 rows. Cast off, dec 8 sts evenly across cast off row by working 2 sts tog before casting off.

FRONT: Work as Back until armhole is 2 (2¼: 2½: 2¾) ins less than back, meas down from highest point of shoulder shaping, fin with a W.S. row.

Shape Neck:

Next row: Ptn until 37 (39: 41: 43) sts rem, cast off next 12 sts, ptn to end.

Cont on last set of sts leaving sts on other side until required. Keeping armhole edge straight, work 4 (6: 8: 10) rows, dec one st at neck edge every row, fin at armhole edge.

Shape Shoulder: Cont dec at neck edge for next 5 (3: 2: 0) rows but **AT THE SAME TIME** shape shoulder by casting off 6 (6: 7: 7) sts from armhole edge at beg next 1 (3: 1: 3) alt rows, then cast off 5 (0: 6: 0) sts from same edge at beg 2 (0: 2: 0) alt rows. Return to sts left on other side. Rejoin w/ at neck edge and work to match completed side, all shapings reversed.

LEFT SLEEVE: With No. 8 pins cast on 35 (37: 39: 41) sts and work in rib as back band for 12 rows, inc one st at each end and 9 sts evenly across centre 25 sts of last row. 46 (48: 50: 52) sts.

Change to No. 6 pins and work in ptn as fol:

1st row: K 6 (7: 8: 9) sts, ptn 34 sts as for back, k to end.

2nd row: P 6 (7: 8: 9) sts, ptn 34 sts as for back, p to end.

Now cont as established, working stst each side of centre 34 sts worked as centre panel on back, inc one st at each end of the 7th and every fol 8th row until there are 58 (62: 64: 68) sts. Cont straight until sleeve meas 13 (14½: 16: 16½) ins or desired length, fin with a W.S. row.

Shape Top: Keeping continuity of ptn throughout shaping, cast off 2 (3: 3: 4) sts at beg next 2 rows. Dec one st at each end of the next 4 rows. Work one row without shaping, then dec one st at each end of the next 2 rows. Rep last 3 rows until 30 (32: 30: 32) sts rem. Dec one st at each end of the next 0 (2: 1: 5) rows. Cast off 4 (3: 3: 0) sts at beg next 2 (2: 2: 0) rows. 22 sts rem.

Work straight until saddle shoulder extension meas same as across front shoulder to neck, fin with a R.S. row.

Shape Neck Edge of Extension: Cast off 10 sts at beg next row, then dec one st at shaped edge on fol 6 rows. Cast off rem 6 sts.

RIGHT SLEEVE: Work as for Left Sleeve but with shoulder extension shaping at opposite edge.

NECKBAND: Sew in sleeves and across shoulder extensions, leaving left back shoulder and armhole open (short edge of extensions to front shoulder) joining the 6 cast off sts to the 4 rows at back neck. With No. 8 pins and R.S. facing pick up and k 71 (75: 79: 83) sts evenly around neckline and work in k 1, p 1 rib (beg first row p 1) for 6 rows. Cast off LOOSELY rib-wise.

TO MAKE UP: Press stst parts with a warm iron over a damp cloth. Join rem shoulder, armhole and neckband seam. Join side and sleeve seams. Press all seams.

